

Hafele Dispensa Junior III- User Guide

Contents of this Article...


- Cabinet Properties
- Activating Hardware
- Position Dispensa in a cabinet without a set width
- Set cabinet width to EXACT
- Set cabinet width to ROUNDED

Cabinet Properties



- Drawer Construction (Hafele Dispensa Junior III)
- Drawer Guides (Hafele Dispensa Junior III Anthracite or Drawer Guides (Hafele Dispensa Junior III White)

Activate Hardware - *Start with an empty cabinet...*


1. Section Face > Drawer
2. Properties > Construction > Drawer Box > Hafele Dispensa Junior III
3. Hardware > Drawer Guide Schedule > Hafele Dispensa Junior III Anthracite OR Hafele Dispensa Junior III White



Cabinet Vision Training - Hafele Dispensa Junior III- User Guide



Cabinet Vision Training - Hafele Dispensa Junior III- User Guide





Position Dispensa in a cabinet without a set width - *Stretch cabinet to desired width*

1. Orthographic Face (Smiley Face)
2. *Right click* > Drawer Guide
3. Attributes > Position Left/Right (X) > Select position from drop down list


Use if you need to position a specific dimension

1. Position Left/Right ADJ > (enter desired dimension)

Cabinet Vision Training - Hafele Dispensa Junior III- User Guide




Cabinet Vision Training - Hafele Dispensa Junior III- User Guide



Set cabinet width to EXACT - This option allows for end thickness, in this case 16.3mm

1. Left click the cabinet
2. Attribute > Dispensa-Set Cab Width (DX) > True
3. Attribute > Dispensa-Set Cab Width (Precision) > Exact
4. Cabinet snaps to set widths - *width options are 300.6, 400.6, 450.6, 500.6, 600.6*

Cabinet Vision Training - Hafele Dispensa Junior III- User Guide



Set cabinet width to **ROUNDED**

1. Left click the cabinet
2. Attribute > Dispensa-Set Cab Width (DX) > True
3. Attribute > Dispensa-Set Cab Width (Precision) > Rounded
4. Cabinet snaps to set widths - *width options are 300, 400, 450, 500, 600*

